



Installation guide:

1 Setup **remote workstation** first (PC on which you want physical device to appear):

- Run setup_rw.exe
- Reboot the computer
- Run RemoteWorkstation.exe and input remote workstation settings (or use default)
- Start remote workstation (press "Start" button)




2 Setup **device workstation** (where your physical device is installed):

- Run setup_dw.exe
 - ! *If you shared any devices with the help of earlier versions of COM@nywhere - unplug all shared devices.*
- Run DeviceWorkstation.exe and input device workstation settings: IP address of Remote workstation
- Start Device Workstation by clicking "Start" button
- Insert the device you want to share to Remote Workstation.

PAY ATTENTION!

- Do not restart Device Workstation. If you need to reconnect, just replug the device.
- If you don't see any activity on Remote Workstation, please replug the device ("found new hardware" should appear on Remote workstation side).
- If you don't see any activity on Remote workstation again please reboot machine (and start Device Workstation again).

How to install



Feel the freedom of mobility using COM@nywhere!

Check for more on www.intellidriver.com